

在電腦中設定代理伺服器(Windows) - Moodle教學平台線上影片 Setting the Proxy Server in your computer for Moodle YouTube video

<English in page 2>

在校園宿舍裡使用Moodle教學平台時，
遇到課程使用YouTube影片進行線上影音教學，
請使用代理伺服器就不會計算您的下載流量。

1.開啟「控制台」，選擇「網路和網際網路」


有兩台喔proxy1.asia.edu.tw:3128
proxy2.asia.edu.tw:3128

2.選擇「網際網路選項」



3.在「網際網路 – 內容」視窗，選擇「連線」分頁中的「LAN設定」

4.在「區域網路(LAN)設定」下方的「Proxy伺服器」區塊，設定代理伺服器位址與埠號『proxy2.asia.edu.tw』『3128』，按下確定 即可完成。



5.不使用時請將它刪除。

※您的瀏覽器正在使用代理伺服器瀏覽網路，部分系統或網站會無法連線。請解除瀏覽器的網頁代理功能，您才能夠正常瀏覽網路。

本服務為學生宿舍共享使用，可以同時使用的人數及頻寬資源有限，請勿佔用。

在電腦中設定代理伺服器(Windows) - Moodle教學平台線上影片 Setting the Proxy Server in your computer for Moodle YouTube video


When using the Moodle learning platform,
encountered course uses YouTube videos,
use a proxy server , will not calculate your download traffic in the Dorm.
(Use only on campus Dorm)

1. Open 「Control Panel」, Select 「Network and Internet」
2. Select 「Internet Properties」

We have two servers to support
proxy1.asia.edu.tw:3128
proxy2.asia.edu.tw:3128



3. In 「Internet Properties」, select 「Connections」 page, press 「LAN settings」
4. Under 「Local Area Network (LAN) Setting」 window, have 「Proxy server」 area, setting the proxy server Address 「 proxy2.asia.edu.tw 」 and Port 「 3128 」, press 「OK」 complete it



5. Delete it when not in use.

✘ Your browser is browse the Internet using a proxy server, part of the system or the site will not connect. Release the browser's web proxy, you will be able to browse the Internet normally.

This service is shared dormitory, "while the number of users" and "bandwidth resources" is limited, do not occupy.